

NAME

mindi – a tool for creating boot/root disks

SYNOPSIS

```
mindi
mindi -v| --version| -V| -version
mindi --findkernel
mindi --makemountlist file
mindi [--max-compressed-size max] --custom parameters
```

DESCRIPTION

mindi creates a set of boot/root floppy disk images and/or a bootable ISO image using files from the system it runs on. **mind**i will try hard to reproduce the environment of its host system including loaded modules to ensure that the system can be booted properly from the created rescue media. **mind**i is used by **monodarchive(8)** to produce the required boot/root floppy or CD images but can also be used stand-alone.

For stand-alone usage, **mind**i is called without any parameters or switches. It will then interactively ask the user for all information required to create a set of boot/root media.

The probably more frequent way of calling **mind**i is non-interactively from **mondoarchive(8)** using the **--custom** switch. All required information is then provided via command line parameters. The sequence of these parameters is listed below.

OPTIONS

-v| --version| -V| -version
Prints the version of **mind**i.

--findkernel
Finds the image of the running kernel in the file system.

--makemountlist *file*
Creates a mount list and writes it to file *file*.

--max-compressed-size *max*
Maximum size for disk image in KB.

--custom *parameters*
Provide all required parameters to **mind**i for non-interactive calling. This usually means a call from **mondoarchive(8)**. The following parameters are used:

- 01) directory to use for temporary files
- 02) directory to put disk images in
- 03) path to kernel image
- 04) tape device
- 05) tape size [MB]
- 06) total number of files in file list
- 07) use LZO [yes|no]
- 08) CD recovery media [yes|no]
- 09) devices to include
- 10) conservative LiLo settings [yes|no]
- 11) number of last file list
- 12) estimated total number of slices
- 13) devices to exclude
- 14) compare mode [yes|no]
- 15) use lilo [yes|no]
- 16) use star (rather than tar) [yes|no]
- 17) internal tape block size [bytes]
- 18) number of differential backup
- 19) make non-bootable [yes|no]

(Blank parameters must be specified as "" on the command line.)

DIAGNOSTICS

mindi writes some output to the console and extensive information to log file */var/log/mindi.log*.
When seeking technical support for **mind**i, please attach this file to your email.

FILES

/var/log/mindi.log

Log file of mindi run. Contains important information to analyze mindi problem reports.

/etc/mindi/deplist.txt

List of files to be included on boot/root disks.

/root/images/mindi/N.tar.gz

Number N of multiple tar balls together containing root file system for rescue media.

/root/images/mindi/all.tar.gz

Single tar ball of root file system for rescue media.

/root/images/mindi/initrd.img

initrd image for bootable ISO image.

/root/images/mindi/mindi-boot.F.img

mindi boot floppy of size F [KB].

/root/images/mindi/mindi-root.F.img

mindi root floppy of size F [KB].

/root/images/mindi/mindi-data.N.img

mindi data floppy number N for boot/root floppies.

/root/images/mindi/mindi.iso

mindi bootable ISO image.

SEE ALSO

mondoarchive(8), mondorestore(8).

See mailing list at <http://www.mondorescue.org> for technical support.

BUGS

The target location for the image files created by **mind**i is hard-coded to */root/images/mindi*.
As a workaround, it is suggested to make */root/images* a symbolic link to the desired location for the image files.

AUTHORS

Bruno Cornec (lead-development) *bcornec_at_users.berlios.de*

Andree Leidenfrost (co-developper) *aleidenf_at_bigpond.net.au*

ORIGINAL AUTHORS

Hugo Rabson (original author) *hugo.rabson_at_mondorescue.org*

Jesse Keating (packaging) *hosting_at_j2solutions.net*

Stan Benoit (testing) *troff_at_naked soul.org*

Mikael Hultgren (docs) *mikael_hultgren_at_gmx.net*